


Surfer Automation and Slideshow Creator



USER GUIDE

CERC

Surfer Automation and Slideshow Creator

User Guide

November 2012

Cambridge Environmental Research Consultants Ltd 3 King's Parade Cambridge CB2 1SJ

Telephone: +44 (0)1223 357773

Fax: +44 (0)1223 357492 Email: help@cerc.co.uk Web: www.cerc.co.uk

CONTENTS

SECTI	ON 1 Introduction	1
1.1	Surfer Automation	
1.2	Slideshow Creator	1
SECTI	ON 2 Automate Surfer Exports	3
	Requirements	
	Step-by-step instructions	
SECTI	ON 3 Slideshow Creator	9
3.1	Requirements	9
3.2	Step-by-step instructions for creating slideshows	10
APPEN	NDIX A Creating Level Files	16
	Finding column numbers	
	Finding max and min values in ADMS output files	
	Creating level files.	

SECTION 1 Introduction

This document describes two spreadsheet programs supplied with your ADMS model: *SurferAutomation.xlt* and *SlideshowCreator.xlt*, that help you visualise your ADMS model output.

1.1 Surfer Automation

The Surfer Automation tool can help speed up the process of creating or recreating plots in Surfer. It can automatically create a number of contour plots in Surfer in one operation saving them in a format chosen by the user. You can create plots from ADMS, ADMS-Roads or ADMS-Urban output files: <code>.gst</code> files, <code>.glt</code> files and <code>.gtd</code> files are all supported. The contour plots can be saved as bitmap <code>.bmp</code> files, Surfer <code>.srf</code> files, <code>.gif</code> files, and ESRI <code>.shp</code> shapefiles.

- Bitmap .bmp format and Surfer .srf file format are useful for reports and presentations.
- *.gif* file format is useful for creating slideshows see section 1.2 below.
- ESRI .shp shapefile format can be useful for importing contour plots into other applications, for example Google Earth and ArcGIS.

To use the *SurferAutomation.xlt* spreadsheet program you will need:

- Microsoft Excel 2000 or later
- Golden Software Surfer 8 or later

1.2 Slideshow Creator

The Slideshow Creator program can convert a set of static .gif images into a slideshow in the form of an animated .gif file. The animated .gif format is supported in a number of programs, for example PowerPoint and Internet Explorer. Slideshows can show how a time-varying release evolves over time, or the development of an episode in an urban area.

The Surfer Automation program and Slideshow Creator can be used in combination, the Surfer Automation program (Section 1.1) creating a series of static *.gif* images from contour plots of ADMS model output and the Slideshow Creator converting these frames into an animated *.gif*.

The Slideshow Creator program selects all the *.gif* images within a selected folder and resizes them to be the same size. It then adds a user-defined caption to each of the images and animates the resultant images into a slideshow (an animated *.gif* file).

To use the *SlideshowCreator.xlt* spreadsheet program you will need:

- Microsoft Excel 2000 or later
- ImageMagick. ImageMagick is free, open source software created by ImageMagick Studio LLC. The ImageMagick installation can be found in the Support\ImageMagick subdirectory of your ADMS model installation directory. To install ImageMagick run the executable in the above directory and follow the instructions that appear. If Image Magick is not installed when you attempt to create a slideshow a warning will appear as shown in Figure 1.1.




Figure 1.1 - Image Magick not installed warning

• We recommend using the QuickTime Player to view slideshows while they are being refined. QuickTime can be downloaded free of charge from www.apple.com.

SECTION 2 Automate Surfer Exports

The spreadsheet program *SurferAutomation.xlt* takes as input .gst, .gtd or .glt files and Surfer level (.lvl) files, uses them to create contour plots in Surfer, and then exports the contour plots as .gif, bitmap .bmp, Surfer .srf file or ESRI.shp shapefiles.

2.1 Requirements

To use the *SurferAutomation.xlt* spreadsheet program you will need:

- Microsoft Excel 2000 or later
- Golden Software Surfer 8 or later (It is important that you use the latest patch for Surfer 8 as there are problems with earlier versions of Surfer 8 freezing.)

Please check with your IT personnel for your organisation's procedures for installing software.

2.2 Step-by-step instructions

- Step 1 Create one or more Surfer level files to be used for the contour plots. A level file (.lvl) controls the appearance of a contour plot in Surfer. Experienced Surfer users will probably already be familiar with the use of level files. APPENDIX A gives a more detailed explanation of their use and how to create them.
- Step 2 Open *SurferAutomation.xlt* in Excel and enable macros. You will find the file in a sub-directory *Templates*\ of your ADMS installation directory.
- Step 3 The Surfer Automation menu will appear as shown in Figure 2.1. Click the Create exports from Surfer button.
- **Step 4** You will see the Create Exports from Surfer worksheet as shown in Figure 2.2.




Figure 2.1 – Surfer Automation menu



Figure 2.2 – Create Exports From Surfer worksheet

Table 2.1 and Table 2.2 describe the values that you need to enter in the Create Exports From Surfer worksheet shown in Figure 2.2:

Inputs relating to all files		
Input	Description	
Folder containing input files	Location of the folder containing your input files (.gst files, .glt files and/or .gtd files)	
Folder containing levels files	Location of the folder where the level files are stored	
Folder for temporary files	Location of the folder where temporary files will be created. This folder must already exist. Surfer Grid files (.grd) are created here. When plotting .gst files, text files for each time period are also created here.	
Folder for output files	Location of the folder where the output files will be created. This folder must already exist.	
Folder containing background images (Surfer 9+ only)	If you have Surfer 9 or later and wish to include a background image, this is the location of the folder containing the background files.	

Table 2.1 - Create Exports from Surfer: input relating to all files

Inputs relating to each file		
Input	Description	
Filename	In this column list the filenames of the .gst, .glt and .gtd files to be plotted. Remember to include the file extension.	
Column to plot	Column number in the file of the pollutant- averaging time output you want to plot. If you want to plot more than one output from the same file, create another row with the same filename and a different column number. The Find column numbers worksheet described in APPENDIX A can help identify the correct columns.	
Levels file	Name of the level file (remember to include the file extension .lvl)	
Background image file	If you have Surfer 9 or later and would like to include a background image, enter the file name of the background image. The background image file must have the co-ordinates embedded within it e.g. a TIFF file with an accompanying world file (.tfw) or an image in GeoTIFF format. See the Surfer help for details.	
Opacity of contours (%)	If you have Surfer 9 or later and are using a background image, enter the opacity of your contours. The opacity must be a percentage between 0 and 100. An opacity of 100% would not allow the background image to be visible; an opacity of 0% would mean the contours would not be visible.	

Table 2.2 – Create Exports from Surfer: input relating to individual files

Step 5 Click on the Settings button of the Create Exports from Surfer worksheet and the Settings worksheet shown in Figure 2.3 will appear.




Figure 2.3 – Shows the Settings worksheet with default settings.

Step 6 Fill in the Settings sheet shown in Figure 2.3 to control the contour plot production. Table 2.3 and Table 2.4 describe the different parameters.

Output to be produced		
Input	Description	
Bitmap file	Produce a bitmap image.	
Surfer file	Produce a Surfer .srf file. Surfer .srf files can be opened in Surfer and the contour plot copied and pasted into another application, for instance for a report or presentation.	
GIF file	Produce a .gif filegif files are used by the Slideshow Creator program.	
Shp file	Produce an ESRI shapefile. Shapefile format can be useful for exporting contour plots into other applications e.g. Google Earth.	

Table 2.3 – Settings: list of output options. Several options can be selected at once.

Output settings		
Input	Description	
Show colour scale	Tick this box to include a legend in the contour	
	plot. (Shapefiles never include a colour scale.)	
Fill contours	Tick this box to create colour-filled contours.	
Show axes	Tick this box to include axes in the contour plot.	
	(Shapefiles never include axes.)	
Smooth contours	Select the degree of smoothing for the contour	
	lines. See the Surfer help for details.	
Gridding method	Select the gridding method for the contour plot	
	interpolation. See the Surfer help for details.	
Number of grid lines in X	Choose the number of grid lines in the X direction.	
Number of grid lines in Y	Choose the number of grid lines in the Y direction.	
Title on axes	Enter the text for the title of the axes.	
Width in pixels	Enter the width of the image in pixels. The height	
	will be calculated to maintain the aspect ratio of the	
	area being plotted.	

Table 2.4 – Settings: detailed settings

Step 7 Once you have adjusted the Settings, click Return to Input and click the Run! button. Surfer will appear and begin to create the contour plots. Wait until the process has finished.

You will find your output files in the folder you chose for output.

• .glt files contain a single set of ADMS output values from long-term calculations. The Surfer Automation tool produces a single image (output file) for each line in the Create Export from Surfer worksheet. The output files are named InputFilename_Col.* where InputFilename is the name of the original .glt file and Col is the number of the column that was plotted.

• .gst files and .gtd files contain multiple sets of ADMS output values, one for each line of meteorological data. The Surfer Automation tool produces one image (output file) for each met line in a .gst file or .gtd file for the column specified in the Create Export from Surfer worksheet. The output files are named InputFilename_Col_Num.* where InputFilename is the name of the original ADMS model output file, Col is the number of the column that was plotted and Num is the number of the met line in the .gst or .gtd file.

SECTION 3 Slideshow Creator

SECTION 2 described how the Surfer Automation program can be used to create a series of static images in *.gif* files by contour plotting ADMS model output. The Slideshow Creator program can then be used to convert these images into an animated *.gif* file with user-defined captions. The animated *.gif* file format is supported in a number of programs, for example PowerPoint and most web browsers.

3.1 Requirements

To use the *SlideshowCreator.xlt* spreadsheet program you will need:

- Microsoft Excel 2000 or later
- ImageMagick. ImageMagick is free open source software created by ImageMagick Studio LLC. This program was designed to work with ImageMagick version 6.5.4 which can be installed from your ADMS model installation directory, in the subdirectory Support\ImageMagick. To install ImageMagick run the executable in the above directory and follow the instructions that appear. If Image Magick is not installed when you attempt to create a slideshow a warning will appear as shown in Figure 3.1.



Figure 3.1 - Image Magick not installed warning

• We recommend using the QuickTime Player to view slideshows while they are being refined. This is due to some previewing software only showing the first slide of your slideshow i.e. the default Window Vista preview software. QuickTime can be downloaded free of charge from www.apple.com.

Please check with your IT personnel for your organisation's procedures for installing software.

3.2 Step-by-step instructions for creating slideshows

- Step 1 Collect the *gif* image files to be included in the slideshow in a single folder. The slideshow will use the image files in alphabetical order by their file names: you may need to alter the names so that when they are put into alphabetical order, they are in the same order as you want them to appear in the slideshow.
- Step 2 Open *SlideshowCreator.xlt* in Excel and enable macros. You will find the file in a sub-directory *Templates*\ of your ADMS installation directory.
- Step 3 You will see the Create Slideshow from GIF Images worksheet as shown in Figure 3.2.
 - Under Folder containing input files enter the location of the folder where you have collected the .gif files to be included in the slideshow.
 - Under Folder for temporary files enter a folder location where the temporary files will be created. This folder must already exist.
 - Under Folder for output files enter the location where the animated .gif file will be created. This folder must already exist.




Figure 3.2 - Create Slideshow from GIF Images worksheet

Step 4 Click the List Files! button. The program will list all the .gif files in the Folder containing input files, as shown in Figure 3.3.




Figure 3.3 - List Files results

Step 5 For each file you can add a Caption that will appear with the .gif in the slideshow.

You can use Excel formulae and tools to create the captions. For example in Figure 3.4 the first caption was typed by hand and then the Excel auto fill tool was used to create the subsequent captions. See the Excel help for details.




Figure 3.4 – List of files with an accompanying caption for each file

Step 6 Click on the Settings button and the Settings worksheet shown in Figure 3.5 will appear.




Figure 3.5 – Settings worksheet showing the default settings.

Step 7 In the Settings worksheet you can change how the captions are displayed and set the properties of your slideshow. Table 3.1 and Table 3.2 describe the Settings parameters.

Caption settings		
Input	Description	
Font size (points)	Size of the caption for each frame in points. The	
	Caption height (pixels) controls the size of the area	
	available for the caption, and may need to be	
	adjusted if the font size is changed.	
Font	The font to use for the caption. A full list of all the	
	fonts available can be found by clicking Full list of	
	fonts online ¹ on the right.	
Font colour	The colour for the caption text. A list of all the text	
	and background colours that can be used can be	
	found by clicking Full list of colours online ² on the	
	right. This link also explains how to use the RGB	
	colour scheme to use user-defined colours.	
Background colour	The background colour for the caption. See the	
	remarks under Font colour above.	
Position of label	Whether the caption is above the image or below.	
Caption height (pixels)	The size of the area available for the caption, in	
	pixels. See the remarks above under Font size (points).	

Table 3.1 – Caption settings.

Slideshow settings		
Input	Description	
Number of loops	The number of times the slideshow will be repeated.	
	Entering zero will cause the slideshow to repeat	
	indefinitely	
Delay (seconds)	The time for which each slide (image with caption)	
	is displayed.	
Output filename	The filename for the output animated .gif file.	
Height (pixels)	The height of each image in the slideshow in pixels,	
	excluding the caption.	
Width (pixels)	The width of each image in the slideshow in pixels.	

Table 3.2 – Slideshow settings.

The default settings are shown in Figure 3.5. Figure 3.6 shows a slideshow created using the default settings.

http://www.imagemagick.org/discourse-server/viewtopic.php?f=1&t=6233 http://imagemagick.org/script/color.php




Figure 3.6 – Slideshow created with the default settings

- Step 8 Create the slideshow by clicking the Create Slideshow! button on the Create Slideshow from GIF Images worksheet. Once complete a message will appear telling you your animation has been created successfully.
- Step 9 To view the slideshow, right click the animated *.gif* file in Windows Explorer, click Open With...., select QuickTime Player and click Play. See Figure 3.7.




Figure 3.7 - Opening your slideshow

Two folders are created in your temporary directory when the program runs, called Resized and Annotated. Resized contains the files resized to the pixel size entered on your Settings worksheet. Annotated contains the images with their captions. The files created in these directories are deleted each time the program starts to run.

APPENDIX A Creating Level Files

A level file (.lvl) controls the appearance of a contour plot in Surfer. Section A.3 gives step-by-step instructions explaining how to create level files for use with the Surfer Automation tool. First, Sections A.1 and A.2 describe some features of the Surfer Automation tool that help in creating level files. These are, the Find Column Numbers worksheet to help select the column containing the correct pollutant-averaging time to be plotted, and the Find Maximum and Minimum worksheet that determines the range of values that need to be covered by the level file.

A.1 Finding column numbers

The Find Column Numbers worksheet can help you identify the column number of interest (**Error! Reference source not found.**). Select the file of interest, click Find column numbers and the parameters for each column are displayed in the table below.




Figure A.1 - The Find Column Numbers tool within SurferAutomation.xlt

A.2 Finding max and min values in ADMS output files

The default levels created by the ADMS contour plotter are optimized for the values found in the specific ADMS output file being plotted. You may wish to create a single level file that can be used for several different ADMS output files, especially if you are creating an animation, as for comparison purposes the plots should have the same scale.

There is a tool in the program that tells you the maximum and minimum values for each set of output without the need to plot all the files. Knowing the maximum and minimum values then allows a suitable level file to be created. If

you click on Find max and min values on the Surfer Automation menu, it will open this tool – shown in Figure A.2 below.

If you want to find the max and min values across more than one column in the same file, create another row with the same filename, but a different column number.




Figure A.2 - Find max and min values for level file tool within SurferAutomation.xlt

To use the Find max and min values tool, enter the:

Input	Description
Folder containing files	Either enter or browse to the location of the folder
	containing the ADMS model output files
Filename	Input each file's name (remember to enter the file
	extension on the end)
Column to plot	This is the column number within your file of the
	pollutant you want to plot.

Table A.1 – Input values for find maximum and minimum sheet

A.3 Creating level files

- Use the ADMS Contour plotter to plot contours in Surfer from your model output. See the main ADMS manual for details. Remember that the default levels created by the ADMS contour plotter are optimised for the values found in the specific ADMS output file being plotted.
- Step 2 Once the contour plot has been plotted in Surfer, double click on the plot and the Properties window should appear. Go to the Levels tab.




Figure A.3 - ADMS Contour plotter (Plotting in Surfer)




Figure A.4 - Level Properties dialogue box in Surfer

The contour levels can be customized here to control the contour plot appearance. Here you can change the maximum and minimum values so that the level file can be used for multiple plots. See the Surfer help for details. The Save button allows you to save a level file that will reproduce the same appearance in another plot.